

E431U

MULTI-PATTERN CONDENSER USB MICROPHONE

DRIVER USER'S GUIDE

Contact

Marketing and sales

Goang-Fann Co., Ltd.
+886-2-26931323
sales@superlux.com.tw
support@superlux.com.tw

Manufacturing & logistics

Superlux Enterprise
Development (Shanghai) Co., Ltd.

Superlux[®]



[+ View Larger](#)

reproduction. Featuring three different pattern settings, the Superlux E431U makes it easy to select the best pickup pattern for different professional recording requirements.

The Superlux E431U is an ideal choice for a wide range of professional audio vocal, musical instrument, recording, streaming or broadcasting applications.

Features

[Specifications](#)

[Accessories](#)

[Download](#)


General Features

- USB digital recording condenser microphone.
- Multi-pattern function to offer the best pickup pattern under different recording requirements.
- 24 bit, 192 kHz sampling rate.
- Equipped with high quality A/D converter for excellent sound quality.
- Featured with headphone jack and individual volume control for zero-latency monitoring.
- The built-in headphone amplifier ensures extremely clear and rich playback details


STEP 1 Enter www.superlux.com.tw and search “E431U” at the search bar.

Or follow www.superlux.com.tw → Personal Audio → Wired Microphones → USB Microphones and find E431U.


Click the E431U product graphic to enter into the product page




- STEP 2** In the E431U product page, hit “Download” tab and go down to the “Media Files” section. Find the right version of the driver based on the Windows OS system accordingly. Double click the right driver to download





- STEP 3** After download the compressed file, unzip the file. Open the file and find an installation file “BravoHDSwPkgSetup.msi”. Double click “setup.exe” to install




STEP 4 Follow the installation instruction to complete the installation







STEP 5 Installation complete

 System restart required ✕



If you want to complete the installation of this software package, you have to restart the system!
Please click button "Yes" to restart the system right now.
If you want to restart the system later yourself, please click button "No".
(If you click button "Yes", system will be restarted in 60 seconds.)

是(Y)

否(N)

STEP 6 After finishing the installation. The system requires to restart the system. Click button "Yes" to restart the system